# **3DMCAP DOCUMENTATION**

Release 1.0



Empresa Brasileira de Pesquisa Agropecuária Embrapa Informática Agropecuária Ministério da Agricultura, Pecuária e Abastecimento

## **DOCUMENTOS 158**

# **3DMCAP DOCUMENTATION**

## Release 1.0

Thiago Teixeira Santos

*Embrapa Informática Agropecuária Campinas, SP* 2018 Exemplares desta publicação podem ser adquiridos na:

#### Embrapa Informática Agropecuária

Av. Dr. André Tosello, 209 - Cidade Universitária Campinas, SP, Brasil CEP. 13083-886 Fone: (19) 3211-5700 www.embrapa.br/informatica-agropecuaria www.embrapa.br www.embrapa.br/fale-conosco/sac Comitê Local de Publicações da Embrapa Informática Agropecuária

Presidente Stanley R. de M. Oliveira

Secretária-Executiva Carla Cristiane Osawa

Membros Adriana Farah Gonzalez, Carla Geovana do Nascimento Macário, Flávia Bussaglia Fiorini, Jayme Barbedo, Kleber X. Sampaio de Souza, Luiz Antonio Falaguasta Barbosa, Maria Goretti G. Praxedes, Paula Regina K. Falcão, Ricardo Augusto Dante, Sónia Ternes

Suplentes Michel Yamagishi e Goran Nesic

Supervisão editorial Kleber X. Sampaio de Souza

Revisão de texto João Camargo Neto

Normalização bibliográfica Maria Goretti G. Praxedes

Projeto gráfico da coleção Carlos Eduardo Felice Barbeiro

Editoração eletrônica *Flávia Bussaglia Fiorini* 

Imagem da capa Thiago T. Santos

**1st edition** on-line (2018)

Unauthorized reproduction of this publication, or any part of it, constitutes copyright infringement (Law nº 9610).

International Data of Publication Cataloging (CIP) Embrapa Agricultural Informatics

Santos, Thiago Teixeira.

3DMCAP documentation : release 1.0 / Thiago Teixeira Santos. - Campinas : Embrapa Agricultural Informatics, 2018.

20 p. il.: (Documents / Embrapa Agricultural Informatics, ISSN 1677-9274).

1. Photogrammetry. 2. Software. 3. 3D Reconstruction. 4. Image analysis . I. Embrapa Agricultural Informatics. I. Title. II. Series.

CDD 526.982

# Author

## Thiago Teixeira Santos

Computer Scientist, PhD in Computer Science, Researcher at Embrapa Agricultural Informatics, Campinas, SP

# Foreword

Photogrammetry, according to The Photogrammetric Record, is the science of deriving accurate and reliable 3D measurements from images. At Embrapa Agricultural Informatics, photogrammetry is employed in agricultural applications to determine shape, size and structure of plants, fruits, crop fields and even animals.

This document is the user manual of a tool, 3DMCAP, developed by our Automation Group for photogrammetry using a single camera and a notebook computer. Our staff was able to use it to recover the three-dimensional structure of plants in greenhouses and in open fields, including vines, coffee trees, maize, sunflower, soybean eucalyptus trunks. The mains advantage of this tool is to present to the user feedback about the imaging process, allowing on site information about the success of the further 3-D reconstruction step. This avoids frustrating returns to the field to get more imaging data after unsuccessful processing.

The present tool is an open-source software, integrating other pieces of open-source code developed by other research groups in a complete photogrammetry pipeline for 3-D point cloud production from monocular imaging by ordinary cameras. Following the open-source spirit, new contributions are very welcome.

Our wishes are this tool can help other groups around the world the same way it has helped in Embrapa's research projects.

Silvia Maria Fonseca Silveira Massruhá General Head Embrapa Agricultural Informatics

# Summary

Introduction	09
Installation	09
Before starting image acquisition	12
The image acquisition step	15
Multiple view stereo with PMVS	18
References	20

## Introduction

3DMCAP is an application for three-dimensional reconstruction of objects from digital images. It allows an ordinary camera and a computer to operate as a *simple 3-D scanner*. The application assists the user on imaging and computing a cloud of 3-D points, sampling the objects surfaces in three dimensions. Its purpose within Embrapa is the 3-D reconstruction of plants for purposes of automatic measurement in phenotyping and precision agriculture.

You can see what the application is able to do in (Santos et al., 2017).

### **Comments and contributions**

Comments, issues and any feedback can be send using the 3DMCAP repository at GitHub<sup>1</sup>.

## 1. Installation

### 1.1. Running using Docker

The easiest way to install and run 3DMCAP is using our *Docker image*, thsant/3d-mcap. If you have Docker running in a Ubuntu Linux host and a camera connected as /dev/video0, the following command should install and run 3DMCAP for you:

```
$ docker run -it --rm -e DISPLAY=$DISPLAY \
-v /tmp/.X11-unix:/tmp/.X11-unix \
--device /dev/video0 \
-v $HOME/.3dmcap:/home/demeter/.3dmcap -v $HOME/workdir:/home/demeter/workdir \
thsant/3dmcap capture.py
```

Note the command above assumes you have, in your home directory, a directory .3dmcap, containing the configuration file (see Section 2.3 for details), and a workdir directory for saving the results produced by the application in the Docker container.

If you have problems loading the graphical interface, try to execute

\$ xhost +local:root

before the docker run. After the execution, run

```
$ xhost -local:root
```

to return the access controls.

Errors regarding NVIDIA drivers and OpenGL

If you are facing crashes presenting the following error message:

```
libGL error: No matching fbConfigs or visuals found
libGL error: failed to load driver: swrast
```

then you are having issues regarding NVIDIA drivers and OpenGL from Docker. In this case, consider NVIDIA Docker as a workaround.

Visit https://github.com/thsant/3dmcap

#### 1.2. Building 3DMCAP from sources

For users that prefer build the entire system in their own hosts, this is the detailed building process.

```
1.2.1. Dependencies
```

The software depends on:

- Eigen 3;
- OpenCV with Python 2.7 support;

• Our modified version of ORB\_SLAM2. It includes DBoW2 and g2o as the original ORB\_SLAM2[2].

The Python components depend on:

- numpy
- scipy
- Pillow
- wxPython
- ObjectListView
- traits
- traitsui
- mayavi
- PyYAML

3DMCAP have beend tested in **Ubuntu 16.04** and **16.10**.

```
1.2.2. Building
```

We assume /usr/local as the install directory. INSTALL\_PREFIX=/usr/local

Add Eigen (needed by OpenCV and g2o), build-essential and cmake: apt-get install -y build-essential libeigen3-dev cmake

Add OpenCV 3.4 dependencies:

```
apt-get install -y git libgtk2.0-dev pkg-config libavcodec-dev \
libavformat-dev libswscale-dev
apt-get install -y python-dev python-numpy libtbb2 libtbb-dev \
libjpeg-dev libpng-dev libtiff-dev libjasper-dev libdc1394-22-dev
```

Get the OpenCV 3.4.1 sources and extract the files to /usr/local/src. Then build OpenCV:

```
cd /usr/local/src/opencv-3.4.1
mkdir build
cd build
cmake -D CMAKE_BUILD_TYPE=Release -D CMAKE_INSTALL_PREFIX=$INSTALL_PREFIX ..
make -j4
make install
```

Check if the Python module is OK:

python -c 'import cv2; print cv2.\_\_version\_\_'

```
Install Pangolin:
apt-get install -y libglew-dev
cd /usr/local/src
git clone https://github.com/stevenlovegrove/Pangolin.git
cd Pangolin
mkdir build
cd build
cd build
cmake -D CMAKE_INSTALL_PREFIX=$INSTALL_PREFIX ..
make -j4
make install
```

Install our modified ORB-SLAM2 version: apt-get install -y python-pip pip install cython cd /usr/local/src git clone https://github.com/thsant/ORB\_SLAM2.git cd ORB\_SLAM2 ./build.sh cp lib/libORB\_SLAM2.so /usr/local/lib cp Thirdparty/DBoW2/lib/libDBoW2.so /usr/local/lib cp Thirdparty/g20/lib/libg20.so /usr/local/lib cp python/slam.so /usr/local/lib/python2.7/dist-packages/ mkdir /usr/local/share/3dmcap cp Vocabulary/ORBvoc.txt /usr/local/share/3dmcap/

Install PMVS. We recommend pmoulon's version at GitHub:

cd /usr/local/src git clone https://github.com/pmoulon/CMVS-PMVS.git cd CMVS-PMVS/program mkdir build cd build/ cmake -D CMAKE\_INSTALL\_PREFIX=\$INSTALL\_PREFIX .. make -j4 make install

Add other 3DMCAP dependencies:

apt-get install -y python-wxgtk3.0 python-vtk python-tk v4l-utils

Finally, get 3DMCAP code: cd /usr/local/src git clone https://github.com/thsant/3dmcap.git cd 3dmcap pip install -r requirements.txt

#### Configure the environment:

cd /usr/local/src/3dmcap

cp -r dmcap/ /usr/local/lib/python2.7/dist-packages

cp -r ./resources/\* /usr/local/share/3dmcap

```
cp ./dmcap/camcal.py ./dmcap/capture.py /usr/local/bin
```

Edit the **3dmcap.cfg** file and save it to your \$H0ME/.3dmcap directory. You can run **capture.py** to start 3DMCAP.

## 2. Before starting image acquisition

Before using 3DMCAP for your image-based reconstruction, you must complete a few preliminary steps:

- 1. Pick a USB camera supported by Video4Linux.
- 2. Disable camera autofocus functionality, if it is present.
- 3. Calibrate the camera you can use our *camcal.py* utility, included in 3DMCAP distribution.

4. Print the *scaling pattern*, if you wish that 3DMCAP to transform your point cloud to a specific scale (millimetersor inches, for example).

5. Edit your configuration file.

In normal conditions, you should perform this procedure a single time if you intend to use the same camera several times.

### 2.1. Camera selection and calibration

You should use an *USB high-definition camera* that is supported by Video4Linux. We have used the Logitech HD Webcam c920, but other devices should also work.

After connecting your camera, you should *set the focus to infinity* and *turn autofocus off*. Changing focus turn the visual odometry (the estimation of the camera location) a lot harder and the ORB-SLAM2 system (the visual odometry system used by 3DMCAP) will not work properly. You can use the v4l2-ctl tool accomplish this step at the Linux shell:

```
$ v4l2-ctl -d /dev/videol -c focus_auto=0
$ v4l2-ctl -d /dev/videol -c focus_absolute=0
```

The example above assumes your USB camera is connected as /dev/video1. After that, you can use the utility camcal.py, included in the 3DMCAP software, to calibrate the camera. If 1920 × 1080 is the maximum resolution your camera is able to support, you should run camcal.py as the following:

#### \$ camcal.py --device /dev/video1 --fwidth 1920 --fheight 1080

or, if you are using the Docker container:

```
$ docker run -it --rm -e DISPLAY=$DISPLAY \
-v /tmp/.X11-unix:/tmp/.X11-unix \
--device /dev/video1 -v /tmp:/home/demeter/workdir:rw \
v /home/thiago/.3dmcap:/home/demeter/.3dmcap \
thsant/3dmcap camcal.py --device /dev/video1 --fwidth 1920 --fheight 1080
```

You should print the *chessboard pattern* available in the *resources directory* and use the application to capture images of it from multiples views, as seen in Figure 1.



Figura 1. The camera calibration tool camcal.py.

Take a dozen images or more, then click the Calibrate button. Then, save the values to a file using the Save button for further usage.

#### 2.2. Printing the scaling pattern

The scaling pattern (available in the resources directory) is a sheet containing easily detectable markers presenting a known size (Figure 2). Ideally, it should be printed and then laminated (or fixed on a planar surface, as a table for example), forming a rigid planar tablet. 3DMCAP will use this pattern to scale the point cloud to a proper measurement unit and also rotate the cloud to a standard orientation. If you put the scaling pattern in the ground, 3DMCAP can give you a oriented model where the Z axis points upward.



Figura 2. The scaling pattern

## 2.3. The configuration file

The configuration file provides essential information that 3DMCAP needs to work properly. The application looks for a configuration file in four different locations, using the first file it found in the following order:

- 1. \$HOME/.3dmcap/3dmcap.cfg
- 2. /etc/3dmcap.cfg
- 3. /usr/local/share/3dmcap/3dmcap.cfg
- 4. /usr/share/3dmcap/3dmcap.cfg

We recommend users employ the first option, creating a .3dmcap directory in their home directories and placing a 3dmcap.cfg file there. Below we show an example of a working 3dmcap.cfg file:

[camera] width=1920 height=1080

[general] resources\_path=/usr/local/share/3dmcap ref\_distance\_mm=51.5 The *camera* section provides the desired frame resolution. Remember digital cameras support several different resolutions and we recommend the bigger one able to work at 30 Hz. The values for width and height **must be the same** used in the camera calibration step. The *general* section informs the path for the resources directory containing essential files for the application. Also in this section we have ref\_distance\_mm, where you must provide the distance observed between two adjacent markers in your printed scaling pattern. Different printing configurations can create different patterns, so it is important you measure your final scaling pattern and set this value properly (Figure 3).

Finally, the *orbslam* section defines the path to the ORB-SLAM2 YAML file containing the camera calibration and other parameters needed by ORB-SLAM2 system. You should edit the camera calibration values, inserting the values you got using camcal.py. Again, you will find an example in the resources directory.



Figura 3. The scaling pattern reference distance is the distance between the centers of two adjacent black-and-white squares.

# 3. The image acquisition step

The application is started running capture.py:

\$ capture.py

Using Docker, you should employ:

```
docker run -it --rm \
-e DISPLAY=$DISPLAY -v /tmp/.X11-unix:/tmp/.X11-unix \
--device /dev/video0 --device /dev/video1 \
-v /tmp:/home/demeter/workdir:rw \
-v /home/thiago/.3dmcap:/home/demeter/.3dmcap
thsant/3dmcap capture.py
```

Consider the following arguments:

• -e DISPLAY=\$DISPLAY -v /tmp/.X11-unix:/tmp/.X11-unix to make the Docker container use the host X Windows system;

• --device /dev/video0 --device /dev/video1 to make the cameras in the host available to the container;

-v /tmp:/home/demeter/workdir:rw to map the host /tmp directory to the container
 \$HOME/workdir; and

• -v /home/thiago/.3dmcap:/home/demeter/.3dmcap to map the configuration directory in the host to the container.

You can change the host working directory or the host configuration directory to values that make more sense to your personal workflow. Considering the configuration is properly set, you should see the main application screen as shown in Figure 4.

The first step is to use the Settings menu to select the camera to be employed, as shown in Figure 5.

Image acquisition is started pressing *Start new acquisition*. The software will spent a few seconds loading the *visual words* data and then the video frames will be displayed in the camera frame panel.



Figura 4. The capture application main screen.



Figura 5. The camera selection dialog.

#### 3.1. 3-D map initialization

A very important step is the *map initialization*, when the visual odometry system finds the first 3-D points in the scene by stereo vision. The further localization and mapping routines will rely in this initial 3-D map. To get a good initial map, consider these tips at the **very beginning** of the image acquisition:

- translates the camera slowly from left to right;
- · look for textures and salient points, avoid homogeneous surfaces;
- avoid point the camera to a single plane, look for regions displaying objects in different planes.

Once the map is initialized, frames will start to appear in the list at the left of the application window. After that, you can move the camera with more freedom, employing rotations and approximations. However, continue to avoid very fast camera movements. In the case the tracking is lost, move the camera near to a previously visited location: ORB-SLAM will then perform *relocalization*. You can use the pause and resume buttons and the relocalization feature to take a break in long acquisitions steps.

Don't forget to take a few frames of the scaling pattern. There is *no need* to make the pattern visible in every frame, a few frames are sufficient for further scaling and rotation (Figure 6).

Pressing *Finish acquistion* will stop the acquisition procedure. You can use the *Save capture files to...* button to save the data to your prefered path.

8	🕒 🗊 3-Deme	ter PlantCapture		
Fil	e Settings			
	•	ā 🖬 🗖	]	📥 🕈 💩 🕞
#	Frame	Path	ſ	Camera frame
1	Frame 00	/tmp/3dmc-q		
2	Frame 00	/tmp/3dmc-q		
3	Frame 00	/tmp/3dmc-q		
4	Frame 00	/tmp/3dmc-q		
5	Frame 00	/tmp/3dmc-q		
6	Frame 00	/tmp/3dmc-q		
7	Frame 00	/tmp/3dmc-q		
8	Frame 00	/tmp/3dmc-q		
9	Frame 00	/tmp/3dmc-q		
10	Frame 00	/tmp/3dmc-q		
11	Frame 00	/tmp/3dmc-q		
12	Frame 00	/tmp/3dmc-q	1	-D Viewer
13	Frame 00	/tmp/3dmc-q	:	
14	Frame 00	/tmp/3dmc-q		
15	Frame 00	/tmp/3dmc-q		
16	Frame 00	/tmp/3dmc-q		
17	Frame 00	/tmp/3dmc-q		

Figura 6. The capture process. The current frame shows the scaling pattern. However, it is not necessary to have the pattern visible in every frame.

## 4. Multiple view stereo with PMVS

The *Export files to the MVS subsystem* button will create the files needed by PMVS to perform the multiple viewstereo step. After that, you can use *Start 3-D reconstruction* to start PMVS [<sup>2</sup>] (Figure 7). You could also run PMVS directly from the shell other time, avoiding the 3DMCAP interface or employing a PMVS instance running in a morepowerful machine, just using the files exported by 3DMCAP.

PMVS will create a point cloud (Figure 8), stored as a PLY file in pmvs/models/3dmc-3dmodel. cfg.ply at the working directory.

### 4.1. Scaling

Normalize scale and orientation is optional and depends on good images of the scaling pattern.

Asuccessful scaling will produce a PLY file in pmvs/models/3dmc-3dmodel.norm.ply.Assuming that ref\_distance\_mm was properly set and 3DMCAP was able to identify the scaling pattern, users will be able to perform measurements using the point cloud from this PLY in millimeter scale. The normalization step will also orient the 3-D scene, making the scaling pattern the origin of the 3-D space and making the *Z* -axis to point upward, orthogonal to the pattern plate.

<sup>&</sup>lt;sup>2</sup> See http://www.meshlab.net.

#### 4.2. Exploring your point cloud using Meshlab

You can explore your point clouds in different applications. For example, Meshlab1 is a great tool used to explore and manipulate 3-D models (Figure 9). Meshlab provides tools for editing, measuring, polygonal meshing and surface fitting, allowing further analysis based in the clouds created using 3DMCAP.



Figura 7. The multiple view stereo step.



Figura 8. Dense point cloud shown in the application 3-D viewer.



Figura 9. Point cloud as shown in Meshlab.

# References

FURUKAWA, Y.; J. PONCE, J. Accurate, dense, and robust multiview stereopsis, **IEEE Transactions on Pattern Analysis and Machine Intelligence**, v. 32, n. 8, p. 1362-1376, Aug. 2010.

MUR-ARTAL, R.; MONTIEL, J. M. M.; TARDÓS, J. D. ORB-SLAM: a versatile and accurate monocular SLAM system. **IEEE Transactions on Robotics**, v. 31, n. 5, p. 1147-1163, Oct. 2015. DOI: 10.1109/TRO.2015.2463671.

SANTOS, T. T.; BASSOI, L. H.; OLDONI, H.; MARTINS, R. L. Automatic grape bunch detection in vineyards based on affordable 3D phenotyping using a consumer webcam. In: CONGRESSO BRASILEIRO DE AGROINFORMÁTICA, 11., 2017, Campinas. **Ciência de dados na era da agricultura digital**: anais. Campinas: Editora da Unicamp: Embrapa Informática Agropecuária, 2017. p. 89-98. SBIAgro 2017. Disponível em: <a href="http://ainfo.cnptia.embrapa.br/digital/bitstream/item/171151/1/P-Automatic-grape-bunch....pdf">http://ainfo.cnptia.embrapa.br/digital/bitstream/item/171151/1/P-Automatic-grape-bunch....pdf</a>. Acesso em: 3 dez. 2018.







MINISTÉRIO DA AGRICULTURA, PECUÁRIA E ABASTECIMENTO